Get Started

- Overview of AOMEI Data Backuper
- System requirements
- Supported operating systems
- Supported file systems
- Supported storage devices
- Install and uninstall

Backup

- System backup
- Disk Backup
- Partition and Volume Backup
- Backup Options
  - Compression
  - Encryption
  - Splitting
  - Intelligent sector
  - Use VSS
  - Comments
- Backup management
- Incremental and differential

Restore

How to burn AOMEI Data Backuper bootable disc with UltraISO

How to burn AOMEI Data Backuper bootable disc with UltraISO

Burn bootable USB flash drive

1. Download UltraISO and install it. Start the software and click "continue to try" to use trial version;



2. In the main menu select "File"->"Open" add the Backuper_WinPE.iso file to the project;

Copyright © 2009-2012 AOMEI Technology Co., Ltd. All Rights Reserved.

- System Restore
- Disk Restore
- Partition or Volume Restore
- Sector by Sector Restore
- Edit Partitions

Clone

- Disk Clone
- Partition or Volume Clone

Utilities

- Check Image
- Explore Image
- Create Bootable Disk

Support

- Technical Support
- Glossary



3. Then insert your USB drive;
4. In the main menu select "bootable"->"Write Disk Image" to continue;



5. In the popup window, choose your USB disk drive, and select a "write method" and then writing;



Burn bootable CD/DVD

1. The first three steps are the same as "burn bootable USB flash drive".
2. In the main menu, select "Tools"->Burn CD/DVD Image, then it will popup the following window;



3. In the popup window, choose your disc (CD/DVD or Blu-ray Disk), and then click "Burn" button to burn;



At last you can use the bootable CD or USB flash drive to manage your computers.

How to burn bootable CD with BurnAware

1. Launch BurnAware and insert your CD, select "Burn image" in the main window;



2. In the popup window, choose your disc (CD/DVD or Blu-ray Disk) and click "Browse" button to add the ISO file;



3. Finally, click Burn button to burn the ISO file. Then you could use the bootable disc to manage your computers.



How to burn bootable CD with FreeISOBurner

1. Insert your CD-rom, and then launch FreeISOBurner, click "Open" button to add the ISO file, choose your disc (CD/DVD or Blu-ray Disk) in the drive section;

2. Click "Burn" to burn the ISO file, after a while it will be completed.


Free ISO Burner 1.2
www.freeisoburner.com
Free ISO Burner
ISO File
C:\Users\mhf\Desktop_WinPE.iso
Open
Drive
E: ELBY CLONEDRIVE 1.4
E: ELBY CLONEDRIVE 1.4
F: ELBY CLONEDRIVE 1.4
Volume Label:
Cache Size: 32 MB
Burn Speed: Max
Finalize Disc:
Progress
IDLE
Burn
Abort
Close